

OXApi

Intro

The OX-SDK is a set of software libraries and tools to support the integration of the OX into third party applications. It has branches for [C#](#), [C++](#) and [Python](#). For detailed installation and compatibility instructions please read the specific sections, [C#](#) for C# and Python and [C++](#) for C++. The section [Ox](#) describes the commands individually.

Contents

- [C#, Python](#)
- [C++](#)
- [Ox](#)
 - [TimeoutMs](#)
 - [ConfigureActiveUdpStreams\(streamIds\)](#)
 - [ConfigureExposureTime\(exposureTime\)](#)
 - [ConfigureFieldOfView\(limitLeft,limitRight,offset,height\)](#)
 - [ConfigureFieldOfView\(fieldOfView\)](#)
 - [ConfigureFieldOfViewDistance\(limitLeft,limitRight,near,far\)](#)
 - [ConfigureLaserPower\(factor\)](#)
 - [ConfigureNetwork\(useDHCP,staticIP,subnetMask,gateway\)](#)
 - [ConfigureNetwork\(configuration\)](#)
 - [ConfigureProcessInterfaces\(enableModbus,enableOpcUa,enableUdpStreaming,udpDestinationIp,udpDestinationPort,realtimeProtocolId,ioLinkProcessDataLayout\)](#)
 - [ConfigureProfileAlgorithm\(algorithmId\)](#)
 - [ConfigureProfileAlgorithmParameters\(algorithmId,minPeakHeight,thresholdValue,thresholdType,minPeakWidth\)](#)
 - [ConfigureProfileFilter\(movingAverageEnabled,movingAverageLength\)](#)
 - [ConfigureProfileFilter\(profileFilter\)](#)
 - [ConfigureResampling\(enabled,gridValue\)](#)
 - [ConfigureResolution\(xResolution,zResolution\)](#)
 - [ConfigureStartupSetup\(storageNumber\)](#)
 - [ConfigureTimeServer\(useNTP,timeServers\)](#)
 - [ConfigureTrigger\(triggerMode,modeOption,triggerTime,encoderSteps\)](#)
 - [ConfigureUdpStreams\(streamIds\)](#)
 - [ConfigureZAxis\(zAxisId\)](#)
 - [Connect\(\)](#)
 - [Create\(ipAddress,streamingPort\)](#)
 - [CreateStream\(\)](#)
 - [Disconnect\(\)](#)
 - [EnableLongSession\(\)](#)
 - [GetActiveSetup\(\)](#)
 - [GetActiveUdpStreams\(\)](#)
 - [GetAxesInfo\(\)](#)
 - [GetExposureTime\(\)](#)
 - [GetExposureTimeLimits\(\)](#)

- [GetExposureTimeResolution\(\)](#)
- [GetFieldOfView\(\)](#)
- [GetFieldOfViewDistance\(\)](#)
- [GetFieldOfViewInfo\(\)](#)
- [GetFieldOfViewLimits\(\)](#)
- [GetImage\(\)](#)
- [GetImageInfo\(\)](#)
- [GetIntensityProfile\(\)](#)
- [GetLaserPower\(\)](#)
- [GetLaserPowerInfo\(\)](#)
- [GetLaserPowerLimits\(\)](#)
- [GetMeasurement\(\)](#)
- [GetMeasurementInfo\(\)](#)
- [GetMeasurementValuesInfo\(\)](#)
- [GetNetworkConfiguration\(\)](#)
- [GetNumberOfSetups\(\)](#)
- [GetNumberOfTimeServers\(\)](#)
- [GetParameterSetup\(storageNumber\)](#)
- [GetProcessInterfaces\(\)](#)
- [GetProcessInterfacesInfo\(\)](#)
- [GetProfile\(\)](#)
- [GetProfileAlgorithm\(\)](#)
- [GetProfileAlgorithmParameters\(algorithmId\)](#)
- [GetProfileAlgorithmParamsInfo\(\)](#)
- [GetProfileAlgorithmParamsLimits\(algorithmId\)](#)
- [GetProfileAlgorithms\(\)](#)
- [GetProfileFilter\(\)](#)
- [GetProfileFilterLimits\(\)](#)
- [GetProfileInfo\(\)](#)
- [GetResamplingGridValue\(\)](#)
- [GetResamplingInfo\(\)](#)
- [GetResolution\(\)](#)
- [GetResolutionInfo\(\)](#)
- [GetSecondaryData\(\)](#)
- [GetSensorInfo\(\)](#)
- [GetStartupSetup\(\)](#)
- [GetTimeServerConfiguration\(\)](#)
- [GetTrigger\(\)](#)
- [GetTriggerInfo\(\)](#)
- [GetTriggerLimits\(\)](#)
- [GetUdpStreamingInfo\(\)](#)
- [GetZAxis\(\)](#)
- [IsProfileFilterEnabled\(\)](#)
- [IsResamplingEnabled\(\)](#)
- [LoadParameterSetup\(storageNumber\)](#)
- [Login\(role,password\)](#)
- [Logout\(\)](#)
- [ReadAllSettings\(\)](#)
- [ReadSetting\(storageNumber\)](#)
- [ResetAllSettings\(\)](#)

- [ResetSettings\(\)](#)
- [StoreParameterSetup\(storageNumber\)](#)
- [Trigger\(count\)](#)
- [WriteAllSettings\(settings\)](#)
- [WriteSetting\(setting,storageNumber\)](#)
- [OxStream](#)
 - [ErrorOccured](#)
 - [FullQueueHandling](#)
 - [MeasurementAvailable](#)
 - [MeasurementCount](#)
 - [ProfileAvailable](#)
 - [ProfileCount](#)
 - [QueueSize](#)
 - [ReceiveBufferSize](#)
 - [ClearMeasurementQueue\(\)](#)
 - [ClearProfileQueue\(\)](#)
 - [Close\(\)](#)
 - [Dispose\(\)](#)
 - [ReadError\(\)](#)
 - [ReadMeasurement\(\)](#)
 - [ReadProfile\(\)](#)
 - [Start\(\)](#)
 - [Stop\(\)](#)

SDK for C#

Summary

The OX-SDK is a set of software libraries and tools to support the integration of the OX into third party applications.

The SDK is based on the .NET Library 'OXApi.dll' which can be easily integrated into own C# or VB programs or standard software tools like Matlab or TestStand.

In addition there is a python wrapper (oxapi.py) available for the 'OXApi.dll' to use all their features from a python environment.

The OX SDK consists of the following parts:

- A .NET assembly (OXApi.dll) which provides access to all OX configuration and measurement possibilities.
- A python wrapper which allows the use of OxAPI.dll in a python environment.
- A set of examples in C# and Python which demonstrate the OXApi usage.

Folder structure:

\\API\\OXApi.dll	The OX SDK main assembly.
\\API\\oxapi.py	Python wrapper for OXApi.dll.
\\API\\Newtonsoft.Json.dll	Third party Json parser (MIT license, see newtonsoft.json.txt).
\\API\\websocket-sharp.dll	Third party Websocket library (MIT license, see websocket-sharp.txt).
\\OxApiExamples	A C# project which demonstrates the usage of the OXApi.
\\OxPythonExamples	Python examples which demonstrate the usage of the OXApi python wrapper.

Notes:

OXApi:

- The OXApi.dll requires Microsoft .NET Framework 4.6.1 <https://www.microsoft.com/de-ch/download/details.aspx?id=49982>
- Only one configuration connection can be established at one time, so if the Webinterface is active, the OXApi will not be able to connect.

Python:

- You have to add the path of the OXApi.dll and oxapi.py to your python path (e.g. `sys.path.append(r"C:\Program Files\Baumer\OXSDK\API")`).
- In order to use the wrapper, pythonnet (>= 2.4) has to be installed in your python environment. (<https://pypi.org/project/pythonnet/>)

UDP Streaming:

- To use UDP Streaming, the desired streams should be activated by the OXApi or the Webinterface.
- Ensure that the streaming target IP-Address is configured correctly.
- If more than one OX should stream to the same computer, different ports should be used.
- Keep in mind that the windows firewall may block an application from opening an UDP port.

Version history:

- V1.0.0 First release.
- V1.0.2 Changed measurement data layout, this is the minimum SDK version for OX firmware version V1-0-7 or greater.

SDK for C++

Summary

The OX-CPP-SDK is a set of software libraries and tools to support the integration of the OX into third party applications.

The SDK is based on the C++ Library "libOXApi.so which can be easily integrated into own C++ programs.

The OX C++ SDK consists of the following parts:

- A C++ shared library (libOXApi.so) which provides access to all OX configuration and measurement possibilities.
- The C++ Header files to use the library.
- A example in C++ which demonstrate the OXApi usage.

Folder structure:

/usr/lib/libOXApi.so	The OX C++ SDK main shared library.
/usr/include	The OX C++ SDK header files.
/example	A C++ cmake example which demonstrates the usage of the OXApi.

Notes:

OXApi:

- The OXApi.dll requires Ubuntu 18.04 LTS with Boost 1.70
- Only one configuration connection can be established at one time, so if the Webinterface is active, the OXApi will not be able to connect.

UDP Streaming:

- To use UDP Streaming, the desired streams should be activated by the OXApi or the Webinterface.
- Ensure that the streaming target IP-Address is configured correctly.
- If more than one OX should stream to the same computer, different ports should be used.
- Keep in mind that a firewall may block an application from opening an UDP port.

Setup Development System:

- Get Ubuntu 18.04 LTS (AMD64 desktop image) from <https://releases.ubuntu.com/18.04/>
Note: If you only get a black screen while installation, press ESC while Grub menu and then F6 and mark "nomodeset". Then start install.
- Setup Network to get access to the internet
- Run following command in terminal:

```
sudo apt update
sudo apt install build-essential cmake
```
- Install / Upgrade libboost 1.70

```
sudo add-apt-repository ppa:mhier/libboost-latest
sudo apt update
sudo apt install libboost1.70-dev
```

Use SDK example:

- The SDK files are copied to ~/OxApi/
- Create build directory and run build

```
mkdir ~/OxApi/build
cd ~/OxApi/build
cmake ../example
make
```
- Run example (Sensor is accessible under IP 192.168.0.250)

```
./PosConSdk
```
- Edit main in ~/OxApi/example/src/PosConSdk.cpp and run make again to see other Examples

Ubuntu enable SSH:

- ```
sudo apt install openssh-server
sudo ufw allow ssh
```

#### Version history:

- V1.0.0 First release.

## Ox type

---

### Namespace

Baumer.OXApi

### Summary

This class provides several APIs to get profile, measurement and configuration data from the sensor as well as set the sensor configurations.

## TimeoutMs property

### Summary

Gets or sets the timeout for websocket requests in ms.

## ConfigureActiveUdpStreams(streamIds) method

### Summary

This API is used to enable/disable the UDP streams.

Everytime the function is called, only the UDP streams that are passed to the function are enabled and all other streams are disabled.

Send an empty array to disable all UDP streams. You can get the current status of the UDP streams using [GetActiveUdpStreams](#) API.

```
Usage:
uint[] ids = { 0, 1 };
OX.ConfigureActiveUdpStreams(ids); //Stream with Id 0 and 1 will be
enabled and other streams will be disabled.
```

### Parameters

| Name      | Type                            | Description                                           |
|-----------|---------------------------------|-------------------------------------------------------|
| streamIds | <a href="#">System.UInt32[]</a> | An array containing all UDP stream ids to be enabled. |

## ConfigureExposureTime(exposureTime) method

### Summary

Sets the laser exposure time(typically in  $\mu$ s). The exposure time should be within the limits provided by [GetExposureTimeLimits](#) API.

You can read the current exposure time from the sensor using [GetExposureTime](#) API and the Exposure time units from [GetExposureTimeResolution](#) API.

```
Usage:
OX.ConfigureExposureTime(1000); //Sets the exposure time to 1000 μ s.
```

### Parameters

| Name         | Type                          | Description                                    |
|--------------|-------------------------------|------------------------------------------------|
| exposureTime | <a href="#">System.UInt32</a> | Exposure time to be set(typically in $\mu$ s). |

## ConfigureFieldOfView(limitLeft,limitRight,offset,height)

### method

#### Summary

Configures the sensor field of view (z-axis measured in height). Current field of view can be obtained from [GetFieldOfView](#) API.

The unit and precesion of the x and z values of the field of view can be obtained from [GetFieldOfViewInfo](#) API.

The min and max limits for x and z values of the field of view can be obtained from [GetFieldOfViewLimits](#) API.

#### Usage:

```
//To configure the field of view to -36mm to 25mm from left to right
//and 40mm to 10mm from top to bottom in height mode, use:
ox.ConfigureFieldOfView(-36.0, 25.0, 10.0, 30.0);
```

#### Parameters

| Name       | Type                          | Description      |
|------------|-------------------------------|------------------|
| limitLeft  | <a href="#">System.Double</a> | The left limit.  |
| limitRight | <a href="#">System.Double</a> | The right limit. |
| offset     | <a href="#">System.Double</a> | The offset.      |
| height     | <a href="#">System.Double</a> | The height.      |

## ConfigureFieldOfView(fieldOfView) method

#### Summary

Configures the field of view (z-axis measured in height). This API is another variant of [ConfigureFieldOfView](#).

#### Parameters

| Name        | Type                                           | Description                                           |
|-------------|------------------------------------------------|-------------------------------------------------------|
| fieldOfView | <a href="#">Baumer.OXApi.Types.FieldOfView</a> | An object containing the field of view configuration. |

## ConfigureFieldOfViewDistance(limitLeft,limitRight,near,far)

### method

#### Summary

Configures the field of view (z-axis measured in distance from the sensor). Current field of view can be obtained from [GetFieldOfViewDistance](#) API.

## Parameters

| Name       | Type                          | Description        |
|------------|-------------------------------|--------------------|
| limitLeft  | <a href="#">System.Double</a> | The left limit.    |
| limitRight | <a href="#">System.Double</a> | The right limit.   |
| near       | <a href="#">System.Double</a> | The near distance. |
| far        | <a href="#">System.Double</a> | The far distance.  |

## ConfigureLaserPower(factor) method

### Summary

Configures the laser power to one of the predefined values.

Use [GetLaserPowerLimits](#) API to get the list of predefined laser power values.

Use [GetLaserPower](#) to get the current laser power.

### Parameters

| Name   | Type                          | Description                       |
|--------|-------------------------------|-----------------------------------|
| factor | <a href="#">System.Double</a> | The laser power factor to be set. |

## ConfigureNetwork(useDHCP,staticIP,subnetMask,gateway) method

### Summary

Configures the network settings of an Ox sensor. [ConfigureNetwork](#) is an another variant of this API.

Use [GetNetworkConfiguration](#) API to read the current network configuration from the sensor.

```
Usage:
Ox.ConfigureNetwork(false, "192.168.0.250", "255.255.255.0",
"192.168.0.1")
```

### Parameters

| Name       | Type                           | Description                                                                     |
|------------|--------------------------------|---------------------------------------------------------------------------------|
| useDHCP    | <a href="#">System.Boolean</a> | Enables or disables DHCP.                                                       |
| staticIP   | <a href="#">System.String</a>  | The static ip address to be used in case of failure of DHCP. E.g. 192.168.0.250 |
| subnetMask | <a href="#">System.String</a>  | The subnet mask of the network. E.g. 255.255.255.0                              |
| gateway    | <a href="#">System.String</a>  | The gateway address of the network. E.g. 192.168.0.1                            |



## ConfigureNetwork(configuration) method

### Summary

Configures the network settings of an Ox sensor. [ConfigureNetwork](#) is an another variant of this API.

Use [GetNetworkConfiguration](#) API to read the current network configuration from the sensor.

### Parameters

| Name          | Type                                                    | Description                                                                                               |
|---------------|---------------------------------------------------------|-----------------------------------------------------------------------------------------------------------|
| configuration | <a href="#">Baumer.OXApi.Types.NetworkConfiguration</a> | A NetworkConfiguration object containing DHCP state, static ip address, subnet mask, and gateway address. |

## ConfigureProcessInterfaces(enableModbus,enableOpcUa,enableUdpStreaming,udpDestinationIp,udpDestinationPort,realtimeProtocolId,ioLinkProcessDataLayout) method

### Summary

Configures the sensors process interfaces.

Current state of the process interfaces can be obtained using [GetProcessInterfaces](#) API.

### Parameters

| Name                    | Type                           | Description                                                                                                    |
|-------------------------|--------------------------------|----------------------------------------------------------------------------------------------------------------|
| enableModbus            | <a href="#">System.Boolean</a> | Enables or disables Modbus TCP server.                                                                         |
| enableOpcUa             | <a href="#">System.Boolean</a> | Enables or disables OPC UA server.                                                                             |
| enableUdpStreaming      | <a href="#">System.Boolean</a> | Enables or disables UDP streaming.                                                                             |
| udpDestinationIp        | <a href="#">System.String</a>  | Destination ip address for UDP streaming.                                                                      |
| udpDestinationPort      | <a href="#">System.UInt32</a>  | Destination port for UDP streaming.                                                                            |
| realtimeProtocolId      | <a href="#">System.UInt32</a>  | Id of the realtime protocol. IDs can be obtained using <a href="#">GetProcessInterfacesInfo</a> API.           |
| ioLinkProcessDataLayout | <a href="#">System.UInt32</a>  | Id of the IO-Link process data layout. IDs can be obtained using <a href="#">GetProcessInterfacesInfo</a> API. |

## ConfigureProfileAlgorithm(algorithmID) method

## Summary

Configures the algorithm used for profile calculation. List of all available algorithms can be obtained from [GetProfileAlgorithms](#) API.

## Parameters

| Name        | Type                          | Description                                                 |
|-------------|-------------------------------|-------------------------------------------------------------|
| algorithmId | <a href="#">System.UInt32</a> | The id of the algorithm to be used for profile calculation. |

## ConfigureProfileAlgorithmParameters(algorithmId,minPeakHeight,thresholdValue,thresholdType,minPeakWidth)

### method

## Summary

Configures the parameters for a specific profile computation algorithm.

The limits and units of the parameters can be obtained from [GetProfileAlgorithmParamsLimits](#) and [GetProfileAlgorithmParamsInfo](#) APIs respectively.

Get parameters of an algorithm using [GetProfileAlgorithmParameters](#) API.

Usage:

```
OX.ConfigureProfileAlgorithmParameters(0, 20, 12, 1, 5);
```

## Parameters

| Name           | Type                          | Description                           |
|----------------|-------------------------------|---------------------------------------|
| algorithmId    | <a href="#">System.UInt32</a> | The id of the algorithm to configure. |
| minPeakHeight  | <a href="#">System.UInt32</a> | Minimum peak height.                  |
| thresholdValue | <a href="#">System.UInt32</a> | Threshold value.                      |
| thresholdType  | <a href="#">System.UInt32</a> | Type of the threshold.                |
| minPeakWidth   | <a href="#">System.UInt32</a> | Minimum peak width.                   |

## ConfigureProfileFilter(movingAverageEnabled,movingAverageLength) method

## Summary

Enables/Disables and sets the length of the moving average filter which is used to filter the profile points.

The length should be between the min-max limits returned by [GetProfileFilterLimits](#) API.

You can get the current filter status from [GetProfileFilter](#) API.

Usage:

```
OX.ConfigureProfileFilter(true, 5); //Enables the filter and sets the filter length to 5.
```

## Parameters

| Name                 | Type                           | Description                             |
|----------------------|--------------------------------|-----------------------------------------|
| movingAverageEnabled | <a href="#">System.Boolean</a> | Enables or disables the profile filter. |
| movingAverageLength  | <a href="#">System.UInt32</a>  | Length of the moving average filter.    |

## ConfigureProfileFilter(profileFilter) method

### Summary

Enables/Disables and sets the length of the moving average filter which is used to filter the profile points.

Another variant of [ConfigureProfileFilter](#) API.

### Parameters

| Name          | Type                                             | Description                                       |
|---------------|--------------------------------------------------|---------------------------------------------------|
| profileFilter | <a href="#">Baumer.OXApi.Types.ProfileFilter</a> | An object containing the profile filter settings. |

## ConfigureResampling(enabled,gridValue) method

### Summary

Enables/Disables rasterization of the profile and sets the horizontal distance between the profile points to the given value.

The resampling grid value should be between allowed min - max values returned by the [GetResamplingInfo](#) API.

The resampling active status can be queried using [IsResamplingEnabled](#) API and current grid value can be obtained using [GetResamplingGridValue](#) API.

### Parameters

| Name      | Type                           | Description                                     |
|-----------|--------------------------------|-------------------------------------------------|
| enabled   | <a href="#">System.Boolean</a> | Enables or disabled the profile resampling.     |
| gridValue | <a href="#">System.Double</a>  | The grid value used for the profile resampling. |

## ConfigureResolution(xResolution,zResolution) method

### Summary

Configures the x and z resolution.

The current resolution and available resolution values can be obtained from [GetResolution](#) and [GetResolutionInfo](#) APIs respectively.

Usage:

```
OX.ConfigureResolution(2, 4); //Sets the x resolution to 1/2 and z resolution to 1/4
```

## Parameters

| Name        | Type                          | Description                       |
|-------------|-------------------------------|-----------------------------------|
| xResolution | <a href="#">System.UInt32</a> | The x resolution value to be set. |
| zResolution | <a href="#">System.UInt32</a> | The z resolution value to be set. |

## ConfigureStartupSetup(storageNumber) method

### Summary

Sets the startup parameter setup to given preset storage number.

Get the current startup setup number using [GetStartupSetup](#) API.

### Parameters

| Name          | Type                          | Description         |
|---------------|-------------------------------|---------------------|
| storageNumber | <a href="#">System.UInt32</a> | The storage number. |

## ConfigureTimeServer(useNTP,timeServers) method

### Summary

Enables or disables the time synchronization. Sets the IP addresses of the NTP servers.

Current configurations can be read from the sensor using [GetTimeServerConfiguration](#) API.

```
Usage:
string [] TimeServers ={"192.168.10.1","192.168.10.2"};
OX.ConfigureTimeServer(true, TimeServers); //Enables the time servers and sets
the server ip addresses
```

### Parameters

| Name        | Type                            | Description                                                  |
|-------------|---------------------------------|--------------------------------------------------------------|
| useNTP      | <a href="#">System.Boolean</a>  | Enable or disable time synchronization.                      |
| timeServers | <a href="#">System.String[]</a> | Array of strings containing IP addresses of the NTP servers. |

## ConfigureTrigger(triggerMode,modeOption,triggerTime,encoderSteps) method

### Summary

Configures the trigger to a given trigger mode and option. The names and ids of the trigger modes supported by the sensor can be obtained from [GetTriggerInfo](#) API.

The min-max limits for the trigger time and encoder steps can be obtained from [GetTriggerLimits](#) API.

Use [GetTrigger](#) API to obtain current trigger settings.

```
Usage:
OX.ConfigureTrigger(3, 0, 0, 0); //Software trigger mode id: 3
OX.Trigger(numberOfTriggers); //numberOfTriggers: Number of times the
sensor triggers in a free run mode.
```

#### Parameters

| Name         | Type                          | Description                                        |
|--------------|-------------------------------|----------------------------------------------------|
| triggerMode  | <a href="#">System.UInt32</a> | Id of the trigger mode to be set.                  |
| modeOption   | <a href="#">System.UInt32</a> | Id of the trigger mode option to be set.           |
| triggerTime  | <a href="#">System.UInt32</a> | Trigger time to be used in fixedTime trigger mode. |
| encoderSteps | <a href="#">System.UInt32</a> | Encoder steps to be used in encoder trigger mode.  |

## ConfigureUdpStreams(streamIds) method

#### Summary

This API is used to enable/disable the UDP streams.

Everytime the function is called, only the UDP streams that are passed to the function are enabled and all other streams are disabled.

Send an empty array to disable all UDP streams. You can get the current status of the UDP streams using [GetActiveUdpStreams](#) API.

```
Usage:
uint[] ids = { 0, 1 };
OX.ConfigureUdpStreams(ids); //Stream with Id 0 and 1 will be enabled
and other streams will be disabled.
```

#### Parameters

| Name      | Type                            | Description                                           |
|-----------|---------------------------------|-------------------------------------------------------|
| streamIds | <a href="#">System.UInt32[]</a> | An array containing all UDP stream ids to be enabled. |

## ConfigureZAxis(zAxisId) method

#### Summary

Configures the z-axis(e.g. distance or height). Use [GetAxesInfo](#) to obtain all supported z-axes.

#### Parameters

| Name    | Type                          | Description                 |
|---------|-------------------------------|-----------------------------|
| zAxisId | <a href="#">System.UInt32</a> | Id of the z-axis to be set. |

## Connect() method

### Summary

Establishes a connection to the Ox sensor.

Sensor can be configured or measurement data can be read only after establishing a connection to the sensor.

## Create(ipAddress,streamingPort) method

### Summary

This API creates an object of the Ox sensor and returns it.

The object created using this API can be used to connect and interact with the sensor.

No connection will be established by this method. Use Connect() API on the Ox sensor object to connect.

### Parameters

| Name          | Type                          | Description                                                 |
|---------------|-------------------------------|-------------------------------------------------------------|
| ipAddress     | <a href="#">System.String</a> | The ip address of the sensor to connect, e.g. 192.168.0.250 |
| streamingPort | <a href="#">System.UInt32</a> | UDP port used for streaming. Default port number is 1234    |

## CreateStream() method

### Summary

Returns a singleton instance of the streaming client to access profiles and measurements provided by UDP steaming service.

## Disconnect() method

### Summary

Closes the connection to the sensor.

## EnableLongSession() method

### Summary

Enables long session timeouts.

## GetActiveSetup() method

### Summary

Returns the active setup number and its saved state.

## GetActiveUdpStreams() method

### Summary

Returns the IDs of all activated UDP streams.

The streams associated with the Ids can be obtained using [GetUdpStreamingInfo](#) API.

UDP streams can be enabled/disabled using [ConfigureActiveUdpStreams](#) API.

## GetAxesInfo() method

### Summary

Returns the ids and names of all supported z-axes (e.g., Distance, Height).

To change to different Z axis mode, use [ConfigureZAxis](#) API.

E.g.: Information below is fetched from OX200 sensor with the help of this API.

| Z Axis Id | Z Axis Name |
|-----------|-------------|
| 1         | height      |
| 0         | distance    |

## GetExposureTime() method

### Summary

Returns the current exposure time of the sensor(typically in  $\mu$ s).

One can get the exposure time units from [GetExposureTimeResolution](#) API.

Use [ConfigureExposureTime](#) to configure the exposure time.

## GetExposureTimeLimits() method

### Summary

Returns the minimum and maximum exposure time values(typically in  $\mu$ s) of the OX sensor.

Use [ConfigureExposureTime](#) to configure the exposure time.

E.g.: Information below is fetched from OX200 sensor with the help of this API.

| Max Exposure Time | Min Exposure Time |
|-------------------|-------------------|
|-------------------|-------------------|

| Max Exposure Time | Min Exposure Time |
|-------------------|-------------------|
| 3000              | 100               |

## GetExposureTimeResolution() method

### Summary

Returns the resolution of the exposure time used in [ConfigureExposureTime](#), [GetExposureTime](#) and [GetExposureTimeLimits](#) APIs.

```
Usage:
String TimeResolutionUnit = OX.GetExposureTimeResolution(); //Returns
µs for OX200 sensor.
```

## GetFieldOfView() method

### Summary

Returns the actual field of view settings(z-axis measured in height) from the sensor containing left limit, right limit, height and offset.

The field of view can be configured using [ConfigureFieldOfView](#) API.

## GetFieldOfViewDistance() method

### Summary

Returns the actual field of view settings(z-axis measured in distance from the sensor) from the sensor.

It contains left limit, right limit, near distance and far distance.

One can configure field of view in distance mode using [ConfigureFieldOfViewDistance](#) API.

## GetFieldOfViewInfo() method

### Summary

Returns the x and z axes units and x and z axes precision for the field of view.

One can configure the Field of View using [ConfigureFieldOfView](#) API.

## GetFieldOfViewLimits() method



## Summary

Returns the actual field of view limits from the sensor. The returned object contains left limit, right limit, min width, min height and max height of the field of view.

Use [GetFieldOfViewInfo](#) to obtain precision as well as units of x and z axes limits.

One can configure the Field of View using [ConfigureFieldOfView](#) API.

E.g.: Information below is fetched from OX200 sensor with the help of this API.

|                        |     |
|------------------------|-----|
|                        |     |
| FOV Max Height(Z)      | 50  |
| FOV Min Height(Z)      | 5   |
| FOV Z Precision        | 10  |
| FOV Z Unit             | mm  |
| FOV Max X              | 36  |
| FOV Min X              | -36 |
| FOV Min Width(Delta X) | 2   |
| FOV X Precision        | 10  |
| FOV X Unit             | mm  |

## GetImage() method

### Summary

Returns the last measured raw image from the sensor containing a pixel array (integers 0-255), ROI height, ROI width, Row and Column binning and offset.

```
Usage:
var image = OX.GetImage();
var pixels = image.Pixels; //Array of grayscale pixels
var roiHeight = image.RoiHeight;
var roiWidth = image.RoiWidth;
var rowBinning = image.RowBinning;
var rowOffset = image.RowOffset;
```

## GetImageInfo() method

### Summary

Returns information about the image sensor height, width and max ROI pixel count.

## GetIntensityProfile() method

### Summary

Returns the last measured intensity profile from the sensor.

This API delivers intensity information of the profile points in addition to the information returned by [GetProfile](#) API.

Usage:

```
var profile = OX.GetIntensityProfile();
var xdata = (profile.X[i] + profile.XStart) / profile.Precision;
var zdata = profile.Z[i] / profile.Precision;
var intensity = profile.I[i];
var profile_info = OX.GetProfileInfo();
var xunits = profile_info.XUnits;
var zunits = profile_info.ZUnits;
```

## GetLaserPower() method

### Summary

Returns the current laser power value.

Use [ConfigureLaserPower](#) to configure laser power.

## GetLaserPowerInfo() method

### Summary

Returns laser power factor precision and unit.

## GetLaserPowerLimits() method

### Summary

Returns all predefined laser power factors along with the min and max power factor values.

Use [ConfigureLaserPower](#) to change the laser power factor.

E.g.: Information below is fetched from OX200 sensor with the help of this API.

| Max Power | Min Power | Predefined Factors |
|-----------|-----------|--------------------|
| 3         | 0,5       | 3, 2, 1, 0,5,      |

## GetMeasurement() method

### Summary

Returns an array of latest measurement values, digital output values, encoder value, alarm status, measurement rate, quality id and timestamp.

Use [GetMeasurementInfo](#) API to know more about QualityId and units of TimeStamp.

Use [GetMeasurementValuesInfo](#) API to know more about tool name, id, mode and other metadata associated with the measurement results returned by this API.

#### Usage:

```
var MeasValues = OX.GetMeasurement();
var MeasResults = MeasValues.Values //Double array containing values of enabled tools
var DigitalOuts = MeasValues.DigitalOuts; // Boolean array containing digital outputs
var Alarm = MeasValues.Alarm; //Alarm status
var TimeStamp = MeasValues.TimeStamp;
var QualityId = MeasValues.QualityId;
var MeasurementRate = MeasValues.MeasurementRate;
var ConfigMode = MeasValues.ConfigMode;
var EncoderValue = MeasValues.EncoderValue;
```

## GetMeasurementInfo() method

### Summary

Returns the information about measurements such as time stamp units, measurement rate units, measurement rate precision and all quality value names and ids.

#### Usage:

```
var MeasInfo = OX.GetMeasurementInfo();
var QualityValues = MeasInfo.QualityValues; //Array of Id and Name pair.
var TimeStampUnits = MeasInfo.TimeStampUnits; //Array of time stamp units.
var MeasRateUnit = MeasInfo.MeasurementRateUnit;
var MeasRatePrecision = MeasInfo.MeasurementRatePrecision;
```

## GetMeasurementValuesInfo() method

### Summary

Returns the information about the measurement values such as Tool ID, Tool Mode, Tool Name, Unit, Precision and Limits.

```
Usage:
var MeasValuesInfo = OX.GetMeasurementValuesInfo();
var MeasTypes = MeasValuesInfo.MeasurementTypes; //Contains information about all
active measurements.
//Use foreach loop to iterate over all active measurements.
var AnActiveMeas = MeasTypes[0];
var MeasName = AnActiveMeas.Name;
var MeasMode = AnActiveMeas.Mode;
var MeasTool = AnActiveMeas.Tool;
var MeasToolID = AnActiveMeas.ToolId;
var MeasUnit = AnActiveMeas.Unit;
var MeasPrecision = AnActiveMeas.Precision;
var MeasMinValue = AnActiveMeas.Minimum;
var MeasMaxValue = AnActiveMeas.Maximum;
```

## GetNetworkConfiguration() method

### Summary

Returns the current network configuration of the Ox sensor.

The returned object contains DHCP state, static ip address, subnet mask, gateway address and mac address.

You can set the network configuration using [ConfigureNetwork](#) API.

## GetNumberOfSetups() method

### Summary

Returns the total number of sensor configuration preset storages available in the sensor.

## GetNumberOfTimeServers() method

### Summary

Returns the maximum number of time servers supported by the sensor for time synchronization.

## GetParameterSetup(storageNumber) method

### Summary

Returns the sensor configuration data saved in a given preset number as a json string.

### Parameters

| Name          | Type                          | Description         |
|---------------|-------------------------------|---------------------|
| storageNumber | <a href="#">System.UInt32</a> | The storage number. |

## GetProcessInterfaces() method

### Summary

Returns the current state of all sensor process interfaces like modbus and OPCUA state, UDP streaming status, destination UDP port and ip address. You can configure process interfaces using [ConfigureProcessInterfaces](#)

## GetProcessInterfacesInfo() method

### Summary

Returns the ids and names of the available real time protocols(including the id to disable real time communication).

E.g.: Information below is fetched from OX200 sensor with the help of this API.

| Process Id | Process Name |
|------------|--------------|
| 0          | Disabled     |
| 1          | Profinet     |
| 2          | EtherNetIP   |

## GetProfile() method

### Summary

Returns the last measured profile from the sensor.

In addition to X and Z coordinate values of the profile points, the returned object also contains profile length, quality id, xstart, precision, and timestamp.

```
Usage:
var profile = OX.GetProfile();
var xdata = (profile.X[i] + profile.XStart) / profile.Precision;
var zdata = profile.Z[i] / profile.Precision;
var profile_info = OX.GetProfileInfo();
var xunits = profile_info.XUnits;
var zunits = profile_info.ZUnits;
```

## GetProfileAlgorithm() method

## Summary

Returns an id of the algorithm used for profile calculation.

Use [ConfigureProfileAlgorithm](#) to change the profile algorithm.

## GetProfileAlgorithmParameters(algorithmId) method

### Summary

Returns the current configuration parameter values of a specific profile computation algorithm.

Configure profile algorithm parameters using [ConfigureProfileAlgorithmParameters](#) API.

### Parameters

| Name        | Type                          | Description              |
|-------------|-------------------------------|--------------------------|
| algorithmId | <a href="#">System.UInt32</a> | The id of the algorithm. |

## GetProfileAlgorithmParamsInfo() method

### Summary

Returns the units of all profile algorithm parameters.

## GetProfileAlgorithmParamsLimits(algorithmId) method

### Summary

Returns all parameters' min-max limits for a specific profile computation algorithm.

Configure Profile Algorithm Params using [ConfigureProfileAlgorithmParameters](#) API.

```
Usage:
var ParamLimits = OX.GetProfileAlgorithmParamsLimits(algorithmId);
var Limits = ParamLimits.Limits;
var MinPeakHeightParamMin = Limits.MinPeakHeight.Minimum;
var MinPeakHeightParamMax = Limits.MinPeakHeight.Maximum;
var MinPeakWidthParamMin = Limits.MinPeakWidth.Minimum;
var MinPeakWidthParamMax = Limits.MinPeakWidth.Maximum;
var ThresholdValueMin = Limits.ThresholdValue.Minimum;
var ThresholdValueMax = Limits.ThresholdValue.Maximum;
var ThresholdTypes = Limits.ThresholdTypes; //Returns array containing names and
ids of supported types.
```

### Parameters

| Name        | Type                          | Description                           |
|-------------|-------------------------------|---------------------------------------|
| algorithmId | <a href="#">System.UInt32</a> | The profile computation algorithm id. |

## GetProfileAlgorithms() method

### Summary

Returns an object containing a list of names and ids of the profile algorithms supported by the sensor.

Use [ConfigureProfileAlgorithm](#) to use a different profile algorithm.

E.g.: Information below is fetched from OX200 sensor with the help of this API.

| Algorithm Id | Algorithm Name |
|--------------|----------------|
| 0            | max            |
| 1            | upper          |
| 2            | lower          |

## GetProfileFilter() method

### Summary

Returns a profile filter object containing the active status and length of the moving average filter.

The filter can be configured using [ConfigureProfileFilter](#) API.

## GetProfileFilterLimits() method

### Summary

Returns an object containing minimum and maximum allowed profile filter length.

Use [ConfigureProfileFilter](#) to configure the profile filter.

E.g.: Information below is fetched from OX200 sensor with the help of this API.

| Max Filter Length | Min Filter Length |
|-------------------|-------------------|
| 15                | 3                 |

## GetProfileInfo() method

### Summary

Returns information such as max length of the profile(in number of points), x and z axes units of the profile.

```
Usage:
var ProfileInformation = OX.GetProfileInfo();
uint MaxLength = ProfileInformation.MaxLength;
String XUnit = ProfileInformation.XUnit;
String ZUnit = ProfileInformation.ZUnit;
```

## GetResamplingGridValue() method

### Summary

Returns the current resampling grid value and active status of the profile resampling.

Use [ConfigureResampling](#) to enable/disable resampling and change the resampling grid value.

The unit and precision of the returned grid value can be obtained using [GetResamplingInfo](#) API.

## GetResamplingInfo() method

### Summary

Returns the precision, unit, allowed max and min values for the resampling grid value.

E.g.: Information below is fetched from OX200 sensor with the help of this API.

|                 |     |
|-----------------|-----|
|                 |     |
| Max Grid Value  | 2   |
| Min Grid Value  | 0,2 |
| Grid Precision  | 10  |
| Grid Value Unit | mm  |

## GetResolution() method

### Summary

Returns the current x and z resolution values. If the returned value is n then it implies that the current resolution is 1/n times that of max resolution.

One can configure resolution using [ConfigureResolution](#) API.

```
Usage:
var resolution = OX.GetResolution();
uint xResolution = resolution.XResolution;
uint zResolution = resolution.ZResolution;
```

## GetResolutionInfo() method

### Summary

Returns the list of all available x and z resolutions.

One can configure resolution using [ConfigureResolution](#)

E.g.: Information below is fetched from OX200 sensor with the help of this API.



| X Resolution | Z Resolution |
|--------------|--------------|
| 1, 2, 4,     | 1, 2, 4,     |

## GetSecondaryData() method

### Summary

Returns secondary data such as Temperature, Boot-Up counts, Up Time, Operating Voltage and Operation Time.

```
Usage:
var SecondaryData = OX.GetSecondaryData();
uint BootUpCounter = SecondaryData.BootUpCounter;
uint OperatingTime = SecondaryData.OperatingTime;
uint UpTime = SecondaryData.UpTime;
uint Temperature = SecondaryData.Temperature;
uint OperatingVoltage = SecondaryData.OperatingVoltage;
```

## GetSensorInfo() method

### Summary

Returns sensor information such as type of the sensor, serial number, vendor name and the current firmware versions.

```
Usage:
var SensorInfo = OX.GetSensorInfo();
String SensorType = SensorInfo.Type;
String SerialNumber = SensorInfo.SerialNumber;
String VendorName = SensorInfo.VendorName;
String AggregateVersion = SensorInfo.AggregateVersion;
String SoftwareVersion = SensorInfo.SoftwareVersion;
```

## GetStartupSetup() method

### Summary

Returns the parameter setup number which is loaded during startup of the sensor.  
Change the startup setup number using [ConfigureStartupSetup](#) API.

## GetTimeServerConfiguration() method

## Summary

Returns the current NTP time server configuration containing NTP state and time server IP addresses.

The state or addresses of the time servers can be set using [ConfigureTimeServer](#) API.

## GetTrigger() method

### Summary

Returns the current trigger configuration containing encode steps, trigger mode, trigger mode option and trigger time.

Trigger mode can be configured using [ConfigureTrigger](#) API.

## GetTriggerInfo() method

### Summary

Returns the information about all possible trigger configurations (Names and Ids of all trigger modes and supported trigger options).

To configure the trigger, use [ConfigureTrigger](#) API.

E.g.: Information below is fetched from OX200 sensor with the help of this API.

| Mode Id | Mode Name     | Supported Options |
|---------|---------------|-------------------|
| 0       | freerun       | 1                 |
| 1       | extSingleShot | 4                 |
| 2       | fixedTime     | 1                 |
| 4       | encoder       | 1                 |
| 3       | software      |                   |

| Option Id | Option Name        |
|-----------|--------------------|
| 0         | ignoreSyncIn       |
| 1         | runWhileSyncInLow  |
| 2         | runWhileSyncInHigh |
| 3         | risingEdge         |
| 4         | fallingEdge        |
| 5         | bothEdges          |

## GetTriggerLimits() method

### Summary

Returns the min - max limits for trigger time and encoder steps (used in fixed time trigger and encoder trigger modes).

E.g.: Information below is fetched from OX200 sensor with the help of this API.

| Property          | Value   |
|-------------------|---------|
| Max Encoder Steps | 65536   |
| Min Encoder Steps | 3       |
| Max Interval Time | 4000000 |
| Min Interval Time | 500     |

## GetUdpStreamingInfo() method

### Summary

Returns all available UDP stream names and Ids supported by the sensor.

Use [GetActiveUdpStreams](#) API to obtain IDs of all active UDP streams.

Use [ConfigureActiveUdpStreams](#) to enable/disable UDP streams.

E.g.: Information below is fetched from OX200 sensor with the help of this API.

| UDP Stream Id | UDP Stream Name      |
|---------------|----------------------|
| 0             | zProfile             |
| 1             | intensityProfile     |
| 2             | allMeasurementValues |

## GetZAxis() method

### Summary

Returns an id of the current z-axis. Use [GetAxesInfo](#) to check the corresponding name.

To change to different z-axis mode, use [ConfigureZAxis](#) API.

## IsProfileFilterEnabled() method

## Summary

Returns active status of the profile filter.

```
Usage:
if(!OX.IsProfileFilterEnabled())
{
 OX.ConfigureProfileFilter(true, 5);
}
```

## IsResamplingEnabled() method

### Summary

Returns the current status of the profile resampling.

## LoadParameterSetup(storageNumber) method

### Summary

Loads the sensor configuration from a given parameter setup.

### Parameters

| Name          | Type                          | Description         |
|---------------|-------------------------------|---------------------|
| storageNumber | <a href="#">System.UInt32</a> | The storage number. |

## Login(role,password) method

### Summary

This API is used to enter into admin mode in order to change the sensor configuration.

### Parameters

| Name     | Type                          | Description                                               |
|----------|-------------------------------|-----------------------------------------------------------|
| role     | <a href="#">System.String</a> | The requested role. Default value is "admin".             |
| password | <a href="#">System.String</a> | The password for the requested role. Default value is "". |

## Logout() method

### Summary

This API is used to leave admin mode.

## ReadAllSettings() method

### Summary

Reads all settings from the sensor.

### Returns

An encoded string containing all settings.

## ReadSetting(storageNumber) method

### Summary

Reads a setting from the sensor.

### Returns

ConfigureProfileAlgorithmParameters

An encoded string containing one setting.

### Parameters

| Name          | Type                          | Description                                                        |
|---------------|-------------------------------|--------------------------------------------------------------------|
| storageNumber | <a href="#">System.UInt32</a> | The storage number. "0" specifies device configuration parameters. |

## ResetAllSettings() method

### Summary

Clears all saved parameter setups.

## ResetSettings() method

### Summary

Clears a saved parameter setup.

## StoreParameterSetup(storageNumber) method

### Summary

Stores the actual sensor configuration to the desired storage.

### Parameters

| Name          | Type                          | Description         |
|---------------|-------------------------------|---------------------|
| storageNumber | <a href="#">System.UInt32</a> | The storage number. |

## Trigger(count) method

### Summary

Generates a software trigger. The profiles are acquired in free running mode.

The trigger should be configured to software mode using [ConfigureTrigger](#) before using this API

### Parameters

| Name  | Type                          | Description               |
|-------|-------------------------------|---------------------------|
| count | <a href="#">System.UInt32</a> | Number of trigger events. |

## WriteAllSettings(settings) method

### Summary

Writes all settings to the sensor.

### Parameters

| Name     | Type                          | Description                                                             |
|----------|-------------------------------|-------------------------------------------------------------------------|
| settings | <a href="#">System.String</a> | The settings to write as encoded string (e.g. read by ReadAllSettings). |

## WriteSetting(setting,storageNumber) method

### Summary

Writes a settings to the sensor.

### Parameters

| Name          | Type                          | Description                                                        |
|---------------|-------------------------------|--------------------------------------------------------------------|
| setting       | <a href="#">System.String</a> | The setting to write as encoded string (e.g. read by ReadSetting). |
| storageNumber | <a href="#">System.UInt32</a> | The storage number. "0" specifies device configuration parameters. |

## OxStream type

### Namespace

Baumer.OXApi.UdpStreaming

### Summary

This class is used to read data from active UPD streams using various class APIs.

## ErrorOccured property

### Summary

Returns true if at least one error occurred.

## FullQueueHandling property

### Summary

Defines the behavior if the queue is full and new data arrives.  
This enum can be set to 'DropOldest' or 'IgnoreNew' value.

## MeasurementAvailable property

### Summary

Returns true if at least one measurement is available.

## MeasurementCount property

### Summary

The number of queued measurements.

## ProfileAvailable property

### Summary

Returns true if at least one profile is available.

## ProfileCount property

### Summary

The number of queued profiles.

## QueueSize property

### Summary

The length of all queues. The default value is 10000.

## ReceiveBufferSize property

### Summary

The size of the receive buffer in bytes  
If packets are lost increase this buffer size, the size depends on the used system and its load

## **ClearMeasurementQueue()** method

### **Summary**

Clears the measurement queue.

## **ClearProfileQueue()** method

### **Summary**

Clears the profile queue.

## **Close()** method

### **Summary**

Closes the stream.

## **Dispose()** method

### **Summary**

Disposes the instance and releases all resources.

## **ReadError()** method

### **Summary**

Returns one error from the queue (the error will be removed from the queue).  
Throws an exception if the queue is empty.

## **ReadMeasurement()** method

### **Summary**

Returns oldest measurement from the queue (the measurement will be removed from the queue).  
Throws an exception if the queue is empty.

## **ReadProfile()** method



### Summary

Returns the oldest profile from the queue (the profile will be removed from the queue).  
Throws an exception if the queue is empty.

## Start() method

### Summary

Starts reading data from the streaming sensor.

## Stop() method

### Summary

Stops reading data from the streaming sensor.